



eQuate Session Manager

7 May 2008

Table of Contents

- eQuate Session Manager..... 1
 - Available eQuate Applications 1
 - Run Application 1
 - Close Application 1
 - File menu 1
 - Change Reg. Settings Location 1
 - Lock Settings/Unlock Settings 1
 - Profiles..... 1
 - Run-Time Directory 1
 - Script Directory 1
 - Close 1
 - Options menu 1
 - Force Action Reloads..... 1
 - Enter Equals Tab 1
 - Tab on Full Field 1
 - No Trace 2
 - Trace to Window 2
 - Trace to File..... 2
 - Trace to Window and File 2
 - Screen Visible 2
 - Debug Logging 2
 - Transport Trace..... 2
 - Run menu 2
 - Run Application 2
- Profiles 3
 - Application 3
 - User Route 3
 - Save and Close 3
- eQuate User Sign On 5
 - User Id. 5
 - Password 5
- Change eQuate Run-Time Settings Location 7
 - Delete Source Settings..... 7
 - Set..... 7
 - Cancel 7

eQuate Session Manager

The eQuate Session Manager window is where you execute all your application sessions. The applications are setup by your eQuate application administrator and should be cleared through that individual. If an application fails to run properly, please contact that individual for assistance.

Available eQuate Applications

From this list box, select the application (click on the application with the mouse) and click the Run Application button.

Run Application

After selecting the desired application with the mouse, click this button to run the eQuate application.

Close Application

Click this button to terminate the eQuate Session manager.

File menu

Change Reg. Settings Location

Use this selection to change the location of the eQuate registry settings from current user (each user has their own settings) to local machine (all users use the same settings), or visa versa.

Note: This option is not available for eQuate network users.

Lock Settings/Unlock Settings

Use this selection to lock or unlock other options on this menu.

Note: This option is not available for eQuate network users.

Profiles

Use this selection to assign routes to eQuate applications. For users with the eQuate Session Manager installed on their PC, routes are assigned on the eQuate Session Manager since each user may have different routes configured for host access.

Note: This option is not available for eQuate network users. For eQuate network users, routes are assigned by the eQuate Administrator.

Run-Time Directory

Use this selection to point to the run-time directory where the eQuate application databases are located. Normally, this directory would be located on a file server to which the user must have read privileges.

Note: This option is not available for eQuate network users.

Script Directory

Use this selection to point to the directory where the eQuate sign-on script(s) are located.

Note: This option is not available for eQuate network users.

Note: Normally, the above directories are maintained by the person responsible for administering eQuate on your system. If you have any questions regarding the route to use, please contact that person.

Close

Use this selection to exit the session manager.

Options menu

Force Action Reloads

Select this option to always reload an eQuate action file (.act) of a form when an action is invoked. This option allows eQuate actions to be changed while a form is displayed by the eQuate Session Manager.

Enter Equals Tab

Select this option if you are use to using the Enter key on the keyboard act as the Tab key.

Tab on Full Field

Select this option to have the eQuate Session Manager automatically move to the next field on the window when the current field is full. Note: The next field is determined by the person that designed the eQuate application.

No Trace

Set this option (default) when tracing is not needed.

Trace to Window

Set this option to trace the host connection to a window.

Trace to File

Set this option to trace the host connection to a file.

Trace to Window and File

Set this option to trace the host connection to both a window and a file.

Screen Visible

Set this option to make the emulator screen visible.

Debug Logging

Set this option only when directed by the eQuate Administrator or KMSYS Worldwide, Inc.

Transport Trace

Set this option only when directed by the eQuate Administrator or KMSYS Worldwide, Inc.

Run menu

Run Application

After selecting the desired application with the mouse, use this selection to run the eQuate application.

Profiles

This window is used to assign routes to the various applications that the user is allowed to run.

Application

This is the list of applications available to the user. To assign a route to the application, first select the application with the mouse and then select the route from the User Route drop-down list box at the bottom of the window.

User Route

From this drop-down list box, select the route that is to be applied to the eQuate application.

Note: Normally, the route is configured by the person responsible for administering and maintaining eQuate on your system. If you have any questions regarding the route to use, please contact that person.

Save and Close

After assigning one or routes, click this button to save the settings and exit the window.

eQuate User Sign On

This dialog is used to enter the user id and password of the eQuate Session Manager user. Consult the eQuate Administrator for the user id and password assigned to you.

User Id.

In this box, enter the user id of the eQuate Session Manager User.

Password

In this box, enter the password of the eQuate Session Manager User.

Change eQuate Run-Time Settings Location

This dialog is used to switch the location of the eQuate run-time transport settings. The settings may be placed in the Windows Registry in such a manner as to allow multiple users of a single Windows system to maintain their individual configurations. When individual configurations are to be maintained (the default), the settings are placed under HKEY_CURRENT_USER in the registry. On the other hand, if it is desirable for all users of the system to use the same configuration, an option is available to move those settings to the common location, HKEY_LOCAL_MACHINE.

The dialog acts as a toggle between CURRENT_USER and LOCAL_MACHINE; i.e., if your settings are currently stored in CURRENT_USER, the message will indicate that they be moved to LOCAL_MACHINE; if they are in LOCAL_MACHINE, the move would be to CURRENT_USER.

Delete Source Settings

Check this box to delete the settings in their former location. If this box is not checked, the settings will remain in their old location but will NOT be used or updated in any way.

Set

After selecting an option above, click this button to complete the move.

Cancel

Press this button to ignore any selections and return to the previous dialog.

Index

C			
Change eQuate Run-Time Settings Location	7		
E			
eQuate Session Manager.....	1		
		P	
		eQuate User Sign On.....	5
		Profiles	3